ADDRESSING THE NETWORK – IPV4

OBJECTIVES

- Explain the structure IP addressing and demonstrate the ability to convert between 8-bit binary and decimal numbers.
- Given an IPv4 address, classify by type and describe how it is used in the network
- Explain how addresses are assigned to networks by ISPs and within networks by administrators
- Determine the network portion of the host address and explain the role of the subnet mask in dividing networks.
- Given IPv4 addressing information and design criteria, calculate the appropriate addressing components.
- Use common testing utilities to verify and test network connectivity and operational status of the IP protocol stack on a host.



IP ADDRESSING STRUCTURE

 Describe the dotted decimal structure of a binary IP address and label its parts

eneral You can get IP settings assigned this capability. Otherwise, you ne	d automatically if your network supports eed to ask your network administrator for	assigned me an IP address 11000000.1010
the appropriate IP settings.		1000.00000001.
O Obtain an IP address auto	matically	00000101
- 🖲 Use the following IP addre	SS:	Now other
IP address:	192.168.1.5	hosts can find
Subnet mask:		me!
Default gateway:		
C Obtain DNS server addres	s automatically	
Output the following DNS service of the service	ver addresses:	P-20
Preferred DNS server:	· · ·	
Alternate DNS server:	· · ·	
	Advanced	

IP version 4 (IPv4) is the current form of addressing used on the Internet.

Numbering Systems

BINARY NUMBER SYSTEM BINARY AND IPV4 ADDRESSES

- Binary numbering system consists of 1s and 0s, called bits
- Decimal numbering system consists of digits 0 through 9
- Hosts, servers, and network equipment using binary addressing to identify each other.
- Each address is made up of a string of 32 bits, divided into four sections called octets.
- Each octet contains 8 bits (or 1 byte) separated by a dot.
- For ease of use by people, this dotted notation is converted to dotted decimal.



BINARY NUMBER SYSTEM BINARY POSITIONAL NOTATION (CONT.)

The binary positional notation system operates as shown in the tables below.

Radix	2	2	2	2	2	2	2	2
Position in Number	7	6	5	4	3	2	I	0
Calculate	(27)	(26)	(25)	(24)	(23)	(22)	(21)	(20)
Position Value	128	64	32	16	8	4	2	I

Positional Value	128	64	32	16	8	4	2	1
Binary Number (11000000)	I	I	0	0	0	0	0	0
Calculate	1x128	lx64	0x32	0x16	0×8	0x4	0x2	0×1
Add Them Up	128	+ 64	+ 0	+ 0	+ 0	+ 0	+ 0	+ 0
Result	192							

BINARY NUMBER SYSTEM CONVERT BINARY TO DECIMAL

Convert 11000000.10101000.00001011.00001010 to decimal.

Positional Value	128	64	32	16	8	4	2	1	
Binary Number (11000000)	I	I	0	0	0	0	0	0	
Calculate	1×128	Ix64	0x32	0x16	0×8	0x4	0x2	0x1	
Add Them Up	128	+ 64	+ 0	+ 0	+ 0	+ 0	+ 0	+ 0	192
Binary Number (10101000)	I	0	I	0	I.	0	0	0	
Calculate	1×128	0x64	1x32	0x16	lx8	0x4	0x2	0x1	
Add Them Up	128	+ 0	+ 32	+ 0	+ 8	+ 0	+ 0	+ 0	168
Binary Number (00001011)	0	0	0	0	I	0	I	I	
Calculate	0×128	0x64	0x32	0x16	lx8	0x4	lx2	IxI	
Add Them Up	0	+ 0	+ 0	+ 0	+ 8	+ 0	+ 2	+	11
Binary Number (00001010)	0	0	0	0	I.	0	I	0	
Calculate	0×128	0x64	0x32	0x16	lx8	0x4	lx2	0x1	
Add Them Up	0	+ 0	+ 0	+ 0	+ 8	+ 0	+ 2	+ 0	10



BINARY NUMBER SYSTEM DECIMAL TO BINARY CONVERSION

The binary positional value table is useful in converting a dotted decimal IPv4 address to binary.

- Start in the 128 position (the most significant bit). Is the decimal number of the octet (n) equal to or greater than 128?
- If no, record a binary 0 in the 128 positional value and move to the 64 positional value.
- If yes, record a binary 1 in the 128 positional value, subtract 128 from the decimal number, and move to the 64 positional value.
- Repeat these steps through the 1 positional value.



BINARY NUMBER SYSTEM DECIMAL TO BINARY CONVERSION EXAMPLE

- Convert decimal 168 to binary
 - ls 168 > 128?
 - Yes, enter 1 in 128 position and subtract 128 (168-128=40) Is 40 > 64?
 - No, enter 0 in 64 position and move on Is 40 > 32?
 - Yes, enter 1 in 32 position and subtract 32 (40-32=8)
 Is 8 > 16?
 - No, enter 0 in 16 position and move on Is 8 > 8?
 - Equal. Enter 1 in 8 position and subtract 8 (8-8=0) No values left. Enter 0 in remaining binary positions



Decimal 168 is written as 10101000 in binary

BINARY NUMBER SYSTEM

• Routers and computers only understand binary, while humans work in decimal. It is important for you to gain a thorough understanding of these two numbering systems and how they are used in networking.



HEXADECIMAL NUMBER SYSTEM



HEXADECIMAL NUMBER SYSTEM HEXADECIMAL AND IPV6 ADDRESSES

- To understand IPv6 addresses, you must be able to convert hexadecimal to decimal and vice versa.
- Hexadecimal is a base sixteen numbering system, using the digits 0 through 9 and letters A to F.
- It is easier to express a value as a single hexadecimal digit than as four binary bit.
- Hexadecimal is used to represent IPv6 addresses and MAC addresses.

Decimal	
Decimar	
 0	
1	
2	
3	
4	
5	
6	
7	
8	
9	
10	
11	
12	
13	
14	
15	

	Binary
- (0000
	0001
	0010
	0011
	0100
	0101
	0110
	0111
	1000
	1001
	1010
	1011
	1100
	1101
	1110
	1111

Hexadecimal
0
1
2
3
4
5
6
7
8
9
А
В
С
D
E
F

HEXADECIMAL NUMBER SYSTEM HEXADECIMAL AND IPV6 ADDRESSES (CONT.)

- IPv6 addresses are 128 bits in length. Every 4 bits is represented by a single hexadecimal digit. That makes the IPv6 address a total of 32 hexadecimal values.
- The figure shows the preferred method of writing out an IPv6 address, with each X representing four hexadecimal values.
- Each four hexadecimal character group is referred to as a hextet.



HEXADECIMAL NUMBER SYSTEM DECIMAL TO HEXADECIMAL CONVERSIONS

Follow the steps listed to convert decimal numbers to hexadecimal values:

- Convert the decimal number to 8-bit binary strings.
- Divide the binary strings in groups of four starting from the rightmost position.
- Convert each four binary numbers into their equivalent hexadecimal digit.

For example, 168 converted into hex using the three-step process.

- 168 in binary is 10101000.
- 10101000 in two groups of four binary digits is 1010 and 1000.
- 1010 is hex A and 1000 is hex 8, so 168 is A8 in hexadecimal.

CLASSIFY AND DEFINE IPV4 ADDRESSES

• Name the three types of communication in the Network Layer and



CLASSIFY AND DEFINE IPV4 ADDRESSES

 Identify the address ranges reserved for these special purposes in the IPv4 protocol

Reserved IPv4 Address Ranges

Type of Address	Usage	Reserved IPv4 Address Range	RFC
Host Address	used for IPv4 hosts	0.0.0.0 to 223.255.255.255	790
Multicast Addresses	used for multicast groups on a local network	224.0.0.0 to 239.255.255.255	1700
Experimental Addresses	 used for research or experimentation cannot currently be used for hosts in IPv4 networks 	240.0.0.0 to 255.255.255.254	1700 3330

CLASSIFY AND DEFINE IPV4 ADDRESSES

 Identify the historic method for assigning addresses and the issues associated with the method

IP Address Classes								
Address Class	1st octet range (decimal)	1st octet bits (green bits do not change)	Network(N) and Host(H) parts of address	Default subnet mask (decimal and binary)	Number of possible networks and hosts per network			
A	1-127**	0000000- 01111111	N.H.H.H	255.0.0.0	128 nets (2^7) 16,777,214 hosts per net (2^24-2)			
В	128-191	1000000- 10111111	N.N.H.H	255.255.0.0	16,384 nets (2^14) 65,534 hosts per net (2^16-2)			
с	192-223	11000000- 11011111	N.N.N.H	255.255.255 <mark>.0</mark>	2,097,150 nets (2^21) 254 hosts per net (2^8-2)			
D	224-239	11100000- 11101111	NA (multicast)					
E	240-255	11110000- 11111111	NA (experimental)					

** All zeros (0) and all ones (1) are invalid hosts addresses.

PRIVATE ADDRESSES

The private address blocks are:

10.0.0 to 10.255.255.255 (10.0.0.0/8)

172.16.0.0 to 172.31.255.255 (172.16.0.0 / 12)

192.168.0.0 to 192.168.255.255 (192.168.0.0 /16)

ASSIGNING ADDRESSES

 Explain the importance of using a structured process to assign IP addresses to hosts and the implications for choosing private vs. public addresses



ASSIGNING ADDRESSES

• Explain which types of addresses should be assigned to devices other than end user devices

Devices IP Address Ranges							
Use	First Address	Last Address	Summary Address				
Network Address	172.16.x.0		170 16 x 0 /05				
User hosts (DHCP pool)	172.16.x.1	172.16.x.127	172.10.8.0725				
Servers	172.16.x.128	172.16.x.191	172.16.x.128 /26				
Peripherals	172.16.x.192	172.16.x.223	172.16.x.192 /27				
Networking devices	172.16.x.224	172.16.x.253					
Router (gateway)	172.16.x.254		172.16.x.224 /27				
Broadcast	172.16.x.255						



ASSIGNING ADDRESSES

 Describe the process for requesting IPv4 public addresses, the role ISPs play in the process, and the role of the regional agencies that manage IP address registries

Entities that Oversee IP Address Allocation

_	_	_	_	_	_
Global			IANA		
Regional Internet Registries	AfriNIC Africa Region	APNIC Asia/ Pacific Region	LACNIC Latin America And Caribbean Region	ARIN North America Region	RIPE NCC Europe, Middle East, Central Asia Region

SUBNETTING

Subnetting allows for creating multiple logical networks from a single address block. Since we use a router to connect these networks together, each interface on a router must have a unique network ID.

• Use the subnet mask to divide a network into smaller networks and describe the implications of dividing networks for network planners



• Extract network addresses from host addresses using the subnet mask



Calculate the number of hosts in a network range given an address and



 Given a diagram of a multi-layered network, address range, number of hosts in each network and the ranges for each network, create a network scheme that assigns addressing ranges to each network

Given the network address and the subnet mask, define the range of hosts, the broadcast address, and the next network address.

Network Address in decimal	10	187	0	0
Subnet Mask in decimal	255	255	224	0
Network address in binary	00001010	10111011	00000000	00000000
Subnet Mask in binary	11111111	11111111	11100000	00000000
First Usable Host IP Address in decimal	1st octet	2nd octet	3rd octet	4th octet
Last Usable Host IP Address in decimal	1st octet	2nd octet	3rd octet	4th octet
Broadcast Address in decimal	1st octet	2nd octet	3rd octet	4th octet
Next Network Address in decimal	1st octet	2nd octet	3rd octet	4th octet

TESTING THE NETWORK LAYER

 Describe the general purpose of the ping command, trace the steps of its operation in a network, and use the ping command to determine if the IP protocol is operational on a local host





TESTING THE NETWORK LAYER

• Use tracert/traceroute to observe the path between two devices as they communicate and trace the steps of tracert/traceroute's operation



Thank You

6